
# iOS App for Onsite Control of LBNL Isco/CO2 Modules


## AngeloCO2 Rev 2.0 May 2014

Contact: Todd Wood Lawrence Berkeley National Lab (510) 486-4104 tjwood@lbl.gov





Note: This app is not in the Apple Store at this time. For access, please email the Device ID of your iOS device to me at tjwood@lbl.gov and I will respond with an app file to be loaded onto your device through iTunes. Once all controllers in the field are upgraded to wireless I will make the App available through the Apple app store.

### On iOS devie, use Settings to connect to WiFi SSID co2\_net\_0



## Start the AngeloCO2 App





Opening screen. Tap 'Connect'



If connection is OK you will get Green 'Network Ok' message.





There are 3 connection options:

- 1) wired serial (to be deprecated)
- 2) Wifi
- 3) Bluetooth LE

Tapping TCP, BT, Serial will cycle through these modes

Currently not all deployed controllers have all 3 options installed. All except Well1 have Wifi so that is the default choice. Well 1 requires wired serial. I will update the hardware with at Well 1 on the next site visit so that it will use Wifi and BT as well. At that point wired option will be removed from the App. (the wired mode used a private library which means it cannot be placed in the App Store)

Tap Update for a list of Settings. If settings are not displayed then Tap a  $2^{nd}$  time. These are the settings stored in the microcontroller, NOT on the IOS device. Change settings as follows:

Tap the Text box and in the box type: e Addrress Value

e.g.

e 74 5


to set address 74 to a value of 5.

Hit Return to dismiss the keyboard, then Tap Execute to issue the command.

List and rm \* will show and clear files stored on the SD Card of the Box, not the iOS device. Clear the files before Profiling.

Set Date and Set Time sets the controller to the same Time/Date as the iOS device.

Once you have connection to the controller, tap the Profile tab.



Set current Depth in meters by typing values into the text box. This can be updated during the profile. The pump will start when the profile starts (or not, based on eeprom setting DISABLE\_PUMP). The pump can be manually Started/Stopped by tapping 'Pump'. Green indicates it is running, Red indicated the pump is not running.

To start profiling tap 'Start' and text should begin scrolling on the screen. The profile will run indefinitely until Stop is tapped. A temporary file is created called tYYYMMDD\_HHMMSS.pfl

If something happens during profile and the app or board crashes, this file will be available to recover data. If all goes well and profile is terminated by tapping Stop, a data file YYYYMMDD\_HHMMSS.pfl is created and the temp file deleted.

Once a profile is running, values will be updated.

CO2 Value = raw output CO2%\*1000
Therm1 = In well thermistor at intake
Therm2 = a thermistor in cable
Therm3 = a thermistor in the box
%RH = Rel Humidity of gas prior to exhaust
Board = Digital temp chip in center of board
Depth = depth in m input by user (no sensor)

The iOS device's clock and s elapsed since beginning the profile are displayed across the top. At the bottom of the status display is the clock from the board and elapsed time since profiling began. This excludes initial readings of battery voltage, etc so is  $\sim 10$  s less than the iOS elapsed counter. This clock and all settings only update when a new valid reading is taken.

If Stop is tapped and for some reason the button turns to Start but the profile continues to run (i.e. command not received over wireless) the user can type 'stop' in the text box and hot return.

#### Data files:

The profile data is stored in 2 places:

- 1) one the board's SD Card
- 2) on the iOS device

The board's filesystem holds only 32 files then the oldest files are overwritten. The number of files on the iOS device are only limited by available memory.

To get files off of the iOS device:

- 1) plug into computer with the Apple usb cable and start iTunes
- 2) on the left hand side bar under 'Devices' click on your iOS device
- 3) click on Apps at the top of the screen
- 4) scroll down to Fie Sharing and Click AngeloCO2
- 5) click AngeloCO2Data and then 'Save to ..'
- 6) Note this will save the entire directory so click on New Folder to create a place to save the directory. Otherwise you may overwrite previous data.






#### Example profile data file:

./profile

```
Sensor Location Well 00 Depth 4.0 m
CO2 Sensor Serial No 030bd3b7
01-05-2014 16:20:47 Sensor wakeup
01-05-2014 16:20:47 Delay for 00 s
01-05-2014 16:20:47 Sensor Temperature 31.6 C
01-05-2014 16:20:47 Thermistor Temperature 20.8 C, 23.0 C, 28.2 C
01-05-2014 16:20:48 Thermistor Temperature 20.8 C, 22.4 C, 28.3 C
01-05-2014 16:20:48 Thermistor Temperature 21.2 C, 22.8 C, 28.1 C
01-05-2014 16:20:49 0000 Battery [7936549] 8547.8 mv
01-05-2014 16:20:50 Starting Pump
01-05-2014 16:20:50 Sample frequency 1 sample every 2 s.
01-05-2014 16:20:50 Air purge settings: State 1 Purge Start 65
<|01-05-2014|16:20:52|00000|21|-12|14|1|31.6|20.6|22.9|28.2|27.8|26.6|4.0|8.5|1|>
<|01-05-2014|16:20:54|00002|21|-13|13|1|31.6|20.9|22.9|28.3|27.9|25.1|4.0|8.5|1|>
<|01-05-2014|16:20:56|00004|ff|-1|ff|1|31.6|20.8|22.6|28.3|27.9|24.4|4.0|8.5|1|>
./DEPTH 6
<|01-05-2014|16:20:58|00006|21|-16|10|1|31.6|20.5|22.8|28.3|27.9|23.5|4.0|8.5|1|>
<|01-05-2014|16:21:00|00008|21|-15|11|1|31.6|20.4|22.9|28.2|27.9|23.4|6.0|8.5|1|>
<|01-05-2014|16:21:02|00010|21|-13|13|1|31.6|21.1|22.5|28.1|27.9|23.3|6.0|8.5|1|>
<|01-05-2014|16:21:04|00012|21|-15|11|1|31.7|20.9|22.8|28.4|28.1|23.2|6.0|8.5|1|>
<|01-05-2014|16:21:06|00014|21|-13|13|1|31.7|20.6|22.9|28.1|27.9|23.2|6.0|8.5|1|>
<|01-05-2014|16:21:08|00016|21|-13|13|1|31.7|20.5|22.8|28.4|27.9|23.0|6.0|8.5|1|>
<|01-05-2014|16:21:10|00018|21|-14|12|1|31.7|20.9|22.9|28.4|27.9|23.0|6.0|8.5|1|>
<|01-05-2014|16:21:12|00020|21|-15|11|1|31.7|20.6|22.9|28.2|27.9|22.9|6.0|8.5|1|>
<|01-05-2014|16:21:14|00022|21|-15|11|1|31.7|20.6|22.8|28.3|27.9|23.0|6.0|8.5|1|>
<|01-05-2014|16:21:16|00024|21|-16|10|1|31.8|20.6|23.0|28.7|27.9|23.1|6.0|8.5|1|>
<|01-05-2014|16:21:18|00026|ff|-1|ff|1|31.7|21.0|22.9|28.6|27.9|22.9|6.0|8.4|1|>
                                      .... Data omitted ----
<|01-05-2014|16:29:14|00496|21|-8|18|1|30.5|20.9|22.9|24.6|28.1|23.2|67.0|8.4|0|>
<|01-05-2014|16:29:16|00498|21|-8|18|1|30.5|20.8|23.2|24.6|28.0|23.2|67.0|8.4|0|>
<|01-05-2014|16:29:18|00500|21|-8|18|1|30.5|20.9|22.7|24.7|28.1|23.1|67.0|8.4|0|>
<|01-05-2014|16:29:22|00502|21|-9|17|1|30.5|20.8|22.8|24.7|28.0|23.3|67.0|8.4|0|>
<|01-05-2014|16:29:24|00504|21|-9|17|1|30.5|20.7|23.0|24.5|28.0|23.3|67.0|8.4|0|>
01-05-2014 16:29:25 Acquisition Stopped by USER!!
01-05-2014 16:29:25 Stopping Pump
01-05-2014 16:29:25 Sensor Temperature 30.5 C
01-05-2014 16:29:25 Thermistor Temperature 20.9 C, 22.9 C, 25.2 C
01-05-2014 16:29:26 0000 Battery [7829821] 8436.8 mv
01-05-2014 16:29:27 Profile Complete, closing file.
**Done 20140501 162046.pfl **
```


#### **Update:**

Added a switch to select between Manual Profile mode and automated sample mode. Once a profile is started, the switch disappears and is replaced by a button labeled 'Record'. Tapping 'Record' will save the current reading to a summary file with a .rec extension. The full data file still exits with a .pfl extension.




#### **Profile Summary**

3 Records



These are the general App settings which must be entered from the iOS Settings App. Scroll down to AngeloCO2 and enter settings. The Data Directory specifies where on the device the data files will be stored and can be changed. Other settings should be as listed. 'Data Email' and other SMTP settings can be left blank but 'SMTP AUTH Requited' must be OFF.



The WIFI connection and SSID selection of co2 net 0 must be made from the iOS Settings App but the current selection can be viewed from the IPConfig screen. Currently all controllers connect on IP 192.168.1.74 so it should not be necessary to change this although it can be changed from the selection wheel. Tapping 'Set IP' and the 'WiFi Status' will show the new settings. If SSID is null return to iOS Settings App and select co2 net 0 from the WiFi setting. If IP is not 192.168.1.74 select correct setting from the wheel.

## **EEPROM Settings For Profiling Mode**

26 0x01a MODE	0	0x00
28 0x01c CONTROLLER DOWN DELAY	5	0x05
29 0x01d MESSAGE_CHECK_STATUS		0x01
		0x00
30 0x01e MESSAGE_CHECKS_PER_DAY 31 0x01f MESSAGE_CHECK_HR_START 42 0x02a SAMPLES PER DAY	0	0x00
42 0x02a SAMPLES_PER_DAY	12	0x0c
47 0x02f WELL NUMBER	0	0x00
52 0x034 SD PAGE COUNT LOW	355	0x0163
52 0x034 SD_PAGE_COUNT_LOW 54 0x036 SD_START_PAGE_LOW	20	0x0014
82 0x052 CO2_ACQUIRE_S	90	0x5a
83 0x053 CO2_STABILIZATION_S	0	0x00
85 0x055 NO_OF_LOGFILES	21	0x15
87 0x057 SHOW FILE TABLES	0	0x00
90 0x05a PURGE DURING ACQ	1	0x01
91 0x05b PURGE START TIME S	65	0x41
90 0x05a PURGE_DURING_ACQ 91 0x05b PURGE_START_TIME_S 79 0x04f DISABLE_PUMP	0	0x00
92 0x05c DIRECT_FILE_TO_STDOUT	0	0x00
93 0x05d USE_SUBDIRECTORIES	0	0x00
71 0x047 DO_LEV_CHECK	1	0x01
94 0x05e LOG_TEMP	1	0x01
95 0x05f MAX_LEVEL_mv	3800	0x0ed8
48 0x030 TAKE SECOND DEPTH	0	0x00
49 0x031 DEPTH_1 dm 50 0x032 DEPTH_2 dm	40	0x28
50 0x032 DEPTH_2 dm	0	0x00
73 0x049 1/ACQ_FREQUENCY HZ	2	0x02
74 0x04a PROFILE_MINUTES	5	0x05
***** END_EEPROM *****		

For Profiling mode, only the following settings need to be changed:

mp
0.2 Hz
l

e.g. to update WELL\_NUMBER to Well 10:


Pictured below is the Portable CO2 profiler which is used to manually profile wells while on site (as opposed to the permanent installations in various wells). In the latest version, I have added a new comm module which allows both wifi and Bluetooth LE connection from iOS. The enclosure is NEMA4X so is watertight and

can be used in rainy conditions.



Solid green when Wifi connection established

Should Blink when not profiling



Thermistor / ext power